

## Downloading & Installing the Web390 Plug-In

To use IDIS Internet access, you must have the NP3270 (Version 3) or ie3270xp (Version 4) plug-in installed on your PC. Follow these steps to download and install the plug-in.

In your browser go to the "Getting Started" webpage:

Address

<http://www.hud.gov/offices/cpd/systems/idis/gettingstarted/index.cfm>

**Step 3: Install Software**



- Confirm that you have a **compatible Web browser**, properly configured.
- Download and install the appropriate Web 390 plug-in, **Version 3 (version NP3270)** or the **Version 4 (version ie3270xp)** for viewing IDIS screens in a Web browser.
- Refer to the **Plug-in Guide** for step-by-step instructions.
- Download and install the **Report Batch File** for downloading reports from IDIS.
- Refer to the **Report Batch Guide** for step-by-step instructions.

In Step 2 you are going to download one of the two versions of the Web 390 Plug-in. This plug-in is the mechanism that allows your computer to interface with the mainframe that is IDIS.


Based on your organizational set-up, use the table below to identify the proper version of the plug-in needed. Please note that Netscape 4.7 is the only version of the Netscape browser that can be used. Please also note that HUD has tested the Version 4 Plug-in with Windows XP using IE 6.0 and found that it functions properly. HUD makes no other claim regarding the functionality of the Version4 Plug-in.

Operating System	IE 5.0	IE 5.5	IE 6.0	NS 4.7	NS 6.0	NS 6.1	NS 6.2.2
Windows 95	V3	V3	no	V3	no	no	no
Windows 98	V3	V3	no	V3	no	no	no
Windows 2000	V3	no	V4	V3	no	no	no
Windows XP	no	no	V4	V3	no	no	no


Once the proper version of the plug-in has been identified, download it and save it to your computer. In this example, the Version 3 Plug-in was chosen, but the steps are the same for Version 4. Please be sure to remember which directory the file was saved to.




Next, double-click on the file you just downloaded and the installation process will begin.




Click "Next"



Click "Next"



Click "Next"



Click "Finish"

Congratulations, the installation is complete.